

Windows ▼

Mac ▼

Linux ▼

Cloud ▼

Sign In

Bioinformatics Shared Consulting Service

Research efficiently with professional
help

Find Out More

Trusted by



Imperial College
London



a place of mind



UPPSALA
UNIVERSITET



Lawrence Livermore National Laboratory

How To Install and Use NCBI Blast+ on Windows

This page is prepared for the people who want to use NCBI Blast+ on local machines, because we found most of the NCBI Blast+ information available on the Internet is out-dated or inaccurate.

[You can find a review for several installation instructions available on the Internet here.](#) You will be surprised with the results.

This instruction supports newest version of NCBI Blast+ (ver. 2.7.1) released on 10/18/2017.

If you don't like to type blast commands, try [web-based NCBI Blast+](#).

If you have more than 10,000 query sequences and/or large databases > 10GB, we strongly recommend to use cloud providers such as Amazon Web Services.

[Visit here for instructions.](#)

Windows ▼

Mac ▼

Linux ▼

Cloud ▼

Sign In

If you don't understand any part of the instruction below, we recommend you to try [BlastStation2](#) or [BlastStation-Local64](#) to save time. You can start Blast search in less than five minutes with the intuitive manner of operation, amazing easy-to-use interface, and useful extra functions including summary table exporting in CSV format and hit sequence exporting in FASTA format.

Local Blast Search on Windows with BlastStation-Local



1. Installation

32-bit Windows

NCBI Blast+ 2.3.0 or later does not support 32-bit Windows. Even though 64-bit NCBI Blast+ will not start on 32-bit Windows, it can be installed on 32-bit Windows because of the lack of the OS version check function.

- Click the link to download installer from <ftp://ftp.ncbi.nlm.nih.gov/blast/executables/blast+/2.2.30/ncbi-blast-2.2.30+-win32.exe>
- Double click ncbi-blast-2.2.30+-win32.exe to launch installer
- Follow the instructions of installer

All program will be installed under "C:Program Files\NCBI\blast-2.2.30+\bin"

README.txt which contains the link to the BLAST Help web page will be installed in "C:Program Files\NCBI\blast-2.2.30+\doc". [user_manual.pdf](#) is not bundled with the installer anymore.

Uninstaller is found in "C:Program Files\NCBI\blast-2.2.30+".

Windows ▼

Mac ▼

Linux ▼

Cloud ▼

Sign In

- Double click ncbi-blast-2.7.1+-win64.exe to launch installer

- Follow the instructions of installer

All program will be installed under "C:\Program Files\NCBI\blast-2.7.1+\bin"

README.txt which contains the link to the BLAST Help web page will be installed in "C:\Program Files\NCBI\blast-2.7.1+\doc". [user manual.pdf](#) is not bundled with the installer anymore.

Uninstaller is found in "C:\Program Files\NCBI\blast-2.7.1+\".

2. Setup environments

- In order to use NCBI Blast+, Blast database file location should be specified. One option is ncbi.ini file.
- Make ncbi.ini text file in C:\Windows directory. One example is shown below. Since \ should be escaped with \\ in this file, there are two \\s instead of one.

[Click to get ncbi.ini file](#)

- Create BLAST database directory.

1) Open command prompt. If you don't know how to do this, visit <http://www.howtogeek.com/235101/10-ways-to-open-the-command-prompt-in-windows-10/>

2) Type "cd C:\\"

3) Type "mkdir blast\db" and type return.

3. Download database

- Click the link to visit NCBI ftp server. <ftp://ftp.ncbi.nih.gov/blast/db/>
- Double click the database file you want to download, such as nt.00.tar.gz.
- Save the file in C:\blast\db.
- Extract downloaded tar.gz file. If you don't have such a software, [7-zip](#) is convenient.

4. Create database

- Download or create FASTA file. File name is assumed to be testdb.fasta.
- Copy testdb.fasta to C:\blast\db directory using Windows Explorer.
- Open command prompt. If you don't know how to do this, visit <http://www.sevenforums.com/tutorials/947-command-prompt.html> (Windows 7) or <http://www.intowindows.com/how-to-open-command-prompt-as-administrator-in-windows-8-1/> (Windows 8.1) or <http://www.howtogeek.com/235101/10-ways-to-open-the-command-prompt-in-windows-10/> (Windows 10)
- Type "cd C:\blast\db" and type return.
- Type "makeblastdb -in testdb.fasta -out testdb -dbtype nucl" for DNA or "makeblastdb -in testdb.fasta -out testdb -dbtype prot" for Protein and type return to get the database named testdb.
- Type "makeblastdb -help" for advanced options.

5. Launch NCBI-Blast+ commands

- Create dna or protein query FASTA file. It can contain multi FASTA data. File name is assumed to be test_dna.fasta and test_protein.fasta here. nt.00 is a dna database file and nr.00 is a protein database

Windows ▼

Mac ▼

Linux ▼

Cloud ▼

Sign In

2) Type "blastn -query test_dna.fasta -db nt.00 -out test.html -html" and type return.

3) Type "blastn -help" for advanced options.

- blastp

1) Open command prompt.

2) Type "blastp -query test_protein.fasta -db nr.00 -out test.html -html" and type return.

3) Type "blastn -help" for advanced options.

Copyright © 2019 TM Software, Inc. All Rights Reserved.